

TAP SOFTWARE UPDATE INSTALLATION INSTRUCTIONS – REVISION 2.1 - USB

1. File Preparation

- a. Download the file titled softwareUpdate.zip to your computer
- b. Insert USB Flash Drive into computer
- c. Copy softwareUpdate.zip to USB Flash Drive (Figure 1 - Flash Drive Files)




Figure 1 - Flash Drive Files

- d. Right click on softwareUpdate.zip and select “Extract Here” (Figure 2 - Extract Here)




Figure 2 - Extract Here

- e. Safely Remove the USB device from the Computer by selecting “Eject”

2. Installation

- a. With the controller powered OFF insert the USB Flash Drive
- b. Power on the controller
- c. Navigate to Menu > Software Update
- d. Verify Available Versions lists the following: (Figure 3 - Available Versions)
 - 20160307_TAP_controller_R2_1




Figure 3 - Available Versions Example

NOTE: If the above software versions aren't listed, press the back arrow then re-enter the Software Update page by selecting "Software Update"

- e. Select 20160307_TAP_controller_R2_1 and press "Update Software"
- f. At the confirmation dialog, select "Yes"
- g. The controller will now reboot

3. Installation Verification

- a. After the controller reboots, enter the Date and Time and select DONE
- b. Navigate to Menu > Software Update
- c. Verify "Current Software Version" indicates 2.1
- d. Verify the list of Available Versions lists the following:
 - 20160307_TAP_controller_R2_1
- e. Power off the controller and remove the USB Flash Drive